

User's Manual

Release 2.0 August 2, 2010

Copyright and Permission Notice

Portions copyright (c) 2009-2010 Stanford University and Christopher Bruns. Contributors: Vijay Pande, Joy Ku, Jeanette Schmidt, Mark Friedrichs, Peter Eastman

Permission is hereby granted, free of charge, to any person obtaining a copy of this document (the "Document"), to deal in the Document without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Document, and to permit persons to whom the Document is furnished to do so, subject to the following conditions:

This copyright and permission notice shall be included in all copies or substantial portions of the Document.

THE DOCUMENT IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS, CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE DOCUMENT OR THE USE OR OTHER DEALINGS IN THE DOCUMENT.

Acknowledgments

SimTK software and all related activities are funded by the <u>Simbios</u> National Center for Biomedical Computing through the National Institutes of Health Roadmap for Medical Research, Grant U54 GM072970. Information on the National Centers can be found at http://nihroadmap.nih.gov/bioinformatics.

Table of Contents

1	OV	ERVI	EW	1
	1.1	Introd	luction to Molecular Dynamics	1
	1.2	What	is OpenMM Zephyr?	1
		1.2.1	Limitations of OpenMM Zephyr	2
	1.3	What	is OpenMM?	2
		1.3.1	Running OpenMM on GPUs	
		1.3.2	More information about OpenMM	
	1.4	Conve	ntions Used in this Document	
2	IN:	STALI	LING OPENMM ZEPHYR	5
	2.1	Prerec	puisites	5
		2.1.1	Installing VMD (optional but recommended)	2
	2.2	Instal	ling GPU software	6
		2.2.1	Installing CUDA for NVIDIA GPUs	<i>6</i>
		2.2.2	Installing OpenCL	14
	2.3	Gettin	g OpenMM Zephyr	15
		2.3.1	Download OpenMM Zephyr	18
		2.3.2	Install OpenMM Zephyr application	16
		2.3.3	Contents of the OpenMM Zephyr directory	18
3	RU	NNIN	IG A SIMULATION	21
	3.1	Launc	hing OpenMM Zephyr	2 1
	3.2	Choos	ing a Molecule	23
		3.2.1	PDB files	23
		3.2.2	Preparing a PDB file for loading into OpenMM Zephyr	23
	3.3	Select	Location for Output Files	2 4
		3.3.1	What files are saved for a simulation?	24
	3.4	Param	neters	25
		3.4.1	Minimizing energy before dynamic simulation	26
		3.4.2	Choosing the length of time of your simulation	27

		3.4.3 Setting the temperature for your simulation	28
		3.4.4 Choosing a force field for your simulation	28
		3.4.5 Choosing the simulation hardware	29
		3.4.6 Solvent collision interval	3i
		3.4.7 Live viewing in VMD	3i
		3.4.8 Saving trajectory frames	32
		3.4.9 Explicit solvent vs. implicit solvent	32
	3.5	Starting a Simulation	32
	3.6	Restrictions on Simulations in Zephyr	34
		3.6.1 Amber Force Fields	3 4
	3.7	VMD Console	35
	3.8	Final Simulation Results	35
		3.8.1 Saving a trajectory from VMD	35
		3.8.2 Contents of simulation output directory	36
	3.9	Stopping a Simulation	37
	3.10	Modifying Parameters Not Shown in the OpenMM Zephyr GUI (advanced)	37
	3.11	Continuing a Previous Simulation	37
4	TR	OUBLESHOOTING	41
	4.1	Why is my simulation updating in VMD so slowly?	41
	4.2	I am getting the message "Waiting for IMD socket connection to VMD on port 3000"	41
	4.3	The "Simulation complete" message appears but the "Elapsed lab time" does not stop	42
	4.4	I cannot see the full Zephyr screen and am unable to resize the window on the Mac	42
5	GO	ING FURTHER: RUNNING GROMACS-OPENMM FROM THE	
	CO	MMAND LINE	. 43
	5.1	Generating Initial Parameter and Simulation Input Files	43
	5.2	Preparing for a Command Line mdrun_openmm	44
	5.3	Ready to Run	48
	5.4	Restarting a Simulation that Finished Running in Zephyr	49
	5.5	Visualizing Your Trajectory in VMD	50
6	GI	VING BACK: SUBMITTING BUG REPORTS AND FEATURE REQUEST	'S 51
7	AP	PENDIX A: GROMACS-OPENMM LIMITATIONS	53
8	AP	PENDIX B: FFAMBER (AMBER96) PDB NAMING CONVENTIONS	5 5

9	REFERENCES6	5

List of Figures

Figure 2.1: Download VMD from the University of Illinois	5
Figure 2.2: Window for browsing the NVIDIA code samples	7
Figure 2.3: OpenMM Zephyr can be downloaded from Simtk.org	15
Figure 2.4: The Zephyr installer installs some required Microsoft software libra	ries. Click
"Yes" to install these libraries	16
Figure 2.5: Sometimes the installation of the Microsoft libraries takes a while.	Please be
patient	16
Figure 2.6: The installer for OpenMM Zephyr on Mac OS	17
Figure 3.1: Launch Zephyr by double clicking the Zephyr icon for Windows or M	ac (left: or
Windows; right: on Mac OS)	21
Figure 3.2: OpenMM Zephyr application	22
Figure 3.3: Parameters panel	26
Figure 3.4: View when a simulation is running	33
Figure 3.5: VMD can be used to watch the simulation as it runs	34
Figure 3.6: Click "Unblock" to grant permission for Zephyr and VMD to co	mmunicate
through TCP sockets	34
Figure 3.7: VMD console	35
Figure 5.1: Suggested parameter settings to generate initial files to run a	GROMACS
simulation	44
Figure 5.2: Content of testRun directory after initial Zephyr run (files starting v	vith # were
omitted). Note the molecule name in this example was "villin."	45
Figure 5.3: Windows users: Paste commands into your Command Prompt windo	w by right
mouse clicking the top blue bar and selecting Edit→ Paste	45
Figure 6.1: Investigate, submit, or track feature requests and bug reports at Simtk	org51
Figure 8.1: Standard PDB residue name format for RNA and protein in colum	nns 18-20
Column numbers are shown vertically in black.	55
Figure 8.2: PDB atom name fields are in columns 13-16	56

Figure 8.3: Example of a water molecule PDB line. Delete this line and others like it57
Figure 8.4: Example of modifying protein residue names: (top) before editing, (bottom)
after editing
Figure 8.5: Example of modifying initial N-terminal amino acid residue names: (top) Initia
residue HIS 19 before editing. Notice that the initial residue is not always number "1"
(bottom) Initial protein residue after editing. Four character residue name spills into
column 21
Figure 8.6: Modification of final protein residue name: (top) before editing, (bottom) after
editing59
Figure 8.7: Modification of the initial RNA residue: (top) before editing, (bottom) after editing – note the removal of the atoms associated with the phosphate group61
Figure 8.8: Modification of final 3' RNA residue: (top) before editing, (bottom) after editing
Figure 8.9: PDB file excerpt from villin.pdb. Green text shows where atom and residue
names have been changed63

1 Overview

1.1 Introduction to Molecular Dynamics

Researchers are increasingly using molecular dynamics (MD) simulations to model molecular motion and help expand our knowledge and understanding of biology. Examples of how MD simulations have been used include:

- Providing hypotheses for biological phenomena that cannot currently be observed experimentally and guiding new experiments [(Marszalek & al., 1999), (Herce & Garcia, 2007), (Kasson & Pande, 2008)]
- Identifying which engineered molecules would be stable or would bind with another molecule [(Kasson & Pande, 2008)]
- Augmenting information provided by static structures, i.e., from x-ray crystallography [(Glazer, Radmer, & Altman, 2008)]

The potential uses for MD simulations are exciting, but getting started can be overwhelming and time-consuming. OpenMM Zephyr was designed to get researchers running MD simulations quickly.

1.2 What is OpenMM Zephyr?

OpenMM Zephyr is a freely downloadable application with a graphical user interface that allows users to easily run the OpenMM version of <u>GROMACS</u>, a widely used MD package. The OpenMM version speeds up the GROMACS simulations, so that more complex molecules and/or longer processes can be simulated. Read more about OpenMM and how to take full advantage of it in Section 1.3.

OpenMM Zephyr leads the user through the basic steps required to set up and run a simulation, and also to visualize the simulation results using <u>VMD</u>, a popular molecular visualization program. In addition, OpenMM Zephyr displays the specific GROMACS

commands being used, enabling motivated users to teach themselves how to run GROMACS from the command line so that they can eventually use the other options within GROMACS.

1.2.1 Limitations of OpenMM Zephyr

- Supported platforms: Windows XP or Vista, Mac OS 10.5 and 10.6, Linux (with XWindows). Linux versions are built and tested on CentOS5.
- 32 bit operating system (a 64-bit version is also available for Linux)
- Amber 96, Amber 99sb, and Amber 03 force fields only
- Support for only the 20 standard amino acids and 5 canonical nucleotide residues
- For GPU accelerated dynamics:
 - You need to have a supported GPU and drivers (Sections 1.3.1 and 2.2).

1.3 What is OpenMM?

OpenMM is a freely downloadable, high performance, extensible library that allows molecular dynamics simulations to run on high performance computer architectures, such as computer clusters and graphics processing units (GPUs). This makes it more reasonable to simulate complex molecules and/or longer processes. Performance speed ups of over 100X have been achieved in some cases using OpenMM on GPUs. [(Friedrichs, et al., 2009)]. OpenMM Zephyr 2.0 is built using OpenMM Release 2.0.

1.3.1 Running OpenMM on GPUs

Beginning with Preview Release 2, OpenMM enabled fast MD simulations on GPUs. GPUs are computer chips designed for generating computer graphics. Their parallel design makes them also very useful for speeding up a variety of other applications, including MD simulations.

To take advantage of these speed-ups, though, your computer needs to be equipped with one of the supported GPU cards:

Supported NVIDIA GPUs:

http://www.nvidia.com/object/cuda_learn_products.html

Supported ATI GPUs (Note: GPU acceleration currently only supported under Linux):

http://developer.amd.com/gpu/ATIStreamSDK/Pages/default.aspx#two

Your computer does not need one of these GPU cards to run OpenMM Zephyr, but your simulations will not run as fast without one.

1.3.2 More information about OpenMM

You can learn more about the OpenMM project at http://simtk.org/home/openmm.

1.4 Conventions Used in this Document



This warning icon denotes situations that require special attention or caution.



The clicky pointer icon shows where to click on screen shots

2 Installing OpenMM Zephyr

2.1 Prerequisites

OpenMM Zephyr runs on Windows XP, Windows Vista, Mac OS, and Linux (32-bit and 64-bit).

If you wish to use the visualization capabilities of OpenMM Zephyr, you will need to install VMD (see Section 2.1.1).

To take advantage of GPU accelerated molecular dynamics, you must have a supported GPU (see section 1.3.1). You will also need to have the special programming language(s) used for your particular GPU (see Section 2.2).

2.1.1 Installing VMD (optional but recommended)

OpenMM Zephyr also uses the molecular visualization program VMD. If you do not intend on visualizing the MD simulation results within OpenMM Zephyr, you do not need to install VMD. However, to take full advantage of OpenMM Zephyr, it is recommended that you install VMD.




Figure 2.1: Download VMD from the University of Illinois

VMD can be downloaded for free from http://www.ks.uiuc.edu/Research/vmd/. Click on the "Download VMD" link in the left-hand column (Figure 2.1). You will be taken to another webpage, listing all the different versions of VMD. Select the appropriate distribution of the most recent version for your particular platform. Follow the on-line directions to complete the downloading and installation of the program.

2.2 Installing GPU software

If you intend to use GPU accelerated molecular dynamics, you need to install CUDA (for NVIDIA GPUs) or OpenCL and test it before running OpenMM Zephyr.

VMWare, another software for running Windows on a Macintosh, will **not** enable your machine to access the GPU.

2.2.1 Installing CUDA for NVIDIA GPUs

For NVIDIA GPUs, you need to have CUDA version 3.1 or later installed to get the GPU acceleration. OpenCL is included with CUDA for NVIDIA GPUs. It is recommended that you test your installation before trying to run OpenMM and the provided examples.

2.2.1.1 Windows

- 1. Go to http://www.nvidia.com/object/cuda_get.html
- 2. Download and install the CUDA Driver, the CUDA Toolkit, and the CUDA SDK code samples. We recommend using version 3.1, but later versions might work for your machine. The driver and toolkit are needed to get the GPU acceleration. The code samples are required for testing purposes.
- 3. To verify that you've installed things correctly, run a sample program available with the SDK code samples.
 - a. Go to Start -> All Programs -> NVIDIA Corporation -> NVIDIA CUDA SDK -> NVIDIA CUDA SDK Browser

- b. A window appears showing all the different sample programs you can try running (Figure 2.2).
- c. Locate the program "Device Query" and click on the associated "Run" link on the right-hand side. If things are running correctly, a window will appear stating how many devices are running CUDA (there should be at least 1) and that it/they passed the test.




Figure 2.2: Window for browsing the NVIDIA code samples

2.2.1.2 Mac OS X

- 1. Go to http://www.nvidia.com/object/cuda get.html
- 2. Download and install the CUDA Toolkit, CUDA Driver, and the CUDA SDK code samples, version 3.1.
 - a. Install the toolkit using a *custom install* and make sure all boxes, including the kernel extension are checked. Install the CUDA Driver and CUDA SDK

R

code samples, version 3.1. The toolkit and driver are needed to get the GPU acceleration. The code samples are required for testing purposes.

- b. Open a terminal window. Go to Macintosh HD -> Applications -> Utilities.
 Click on Terminal.
- c. Set your environment variables so that your computer can locate the CUDA programs by typing the following two lines:

```
export PATH=/usr/local/cuda/bin:$PATH
export DYLD_LIBRARY_PATH=/usr/local/cuda/lib:
$DYLD_LIBRARY_PATH
```

This sets the environment variables only for the terminal you are in. To set them permanently, you will need to add them to your ~/.bash_profile.

- 3. To verify that you've installed things correctly, run a sample program available with the SDK code samples.
 - a. Within the terminal window, navigate to the location of the code samples. If you installed everything in the default directories, then you would type one of the following (depending on the version of SDK that you downloaded):

```
cd /Developer/GPU Computing/C
```

b. Compile the test programs by typing:

make

c. Navigate to the location of the compiled programs by typing one of the following (depending on the version of SDK that you downloaded):

```
cd /Developer/GPU Computing/C/bin/darwin/release
```

d. Run the deviceQuery program:

./deviceQuery

If things are running correctly, you will see how many devices are running CUDA (there should be at least 1) and a printout saying that it/they passed the test.

Troubleshooting:

If no devices are found, verify that you have a supported GPU card. If you do, re-run the installer and make sure to select a custom installation verifying that all boxes, including the kernel extension, are checked.

If you have multiple GPUs and only one is activated, this may be because of the energy-saving options (this is the case for new MacBook Pros, which ship with a deactivated 9600M GPU). To change the energy-saving options, click System Preferences -> Energy Saver and set the graphics option to "Higher Performance." You will need to log out and then log back in for the new options to take effect.

Additional instructions and troubleshooting tips are provided in the "Getting Started" manual on the CUDA download site.

2.2.1.3 Linux

1. To compile the GPU code on a Linux machine, you will need gcc, version 3.4 or 4.x through 4.2. You can verify the version gcc installed on your system by typing:

2. Go to http://www.nvidia.com/object/cuda get.html

- 3. Download and install the CUDA Driver, the CUDA Toolkit and the CUDA SDK code samples, version 3.1. The toolkit and driver are needed to get the GPU acceleration. The code samples are required for testing purposes. We have tested this for the Redhat Enterprise Linux 5.x version (64-bit). Please refer to the CUDA website and "Getting Started" manual for a list of all supported Linux distributions and additional instructions.
 - a. Open a terminal window.
 - b. If you are running X Windows, you will need to turn it off to install the driver.You can do this by typing as a **superuser**:

```
/sbin/init 3
```

- c. Run the CUDA driver installation script as a **superuser**. If you turned off X Windows, you can turn it on again after the installation is complete (try the commands startx or init 5).
- d. Run the CUDA toolkit installation script as a **superuser**.
- e. Set your environment variables so that your computer can locate the CUDA programs. Or, if you wish to be able to run OpenMM Zephyr by double-clicking the icon through a graphical user interface, you will need to set the library path for the entire system. Please consult your system administrator before changing system-wide configurations.

For the BASH shell (for your individual account)

1. Set your PATH by typing:

```
export PATH=/usr/local/cuda/bin:$PATH
```

2. Set your library path. Depending on whether you use 32-bit or 64bit Linux, type one of the following:

For 32-bit, type (all on one line):

```
export LD_LIBRARY_PATH=/usr/local/cuda/lib:
$LD_LIBRARY_PATH
```

For 64-bit, type (all on one line):

```
export LD_LIBRARY_PATH=/usr/local/cuda/lib64:
$LD LIBRARY PATH
```

These commands set the environment variables **only for the terminal you are in and only for your account. To set them permanently, you will need to add it to ~/.bash_profile or ~/.bashrc

1. Set your PATH by typing:

```
setenv PATH ".:/usr/local/cuda/bin:$PATH"
```

2. Set your library path. Depending on whether you use 32-bit or 64-bit Linux, type one of the following:

```
For 32-bit, type (all on one line):
```

```
setenv LD_LIBRARY_PATH "/usr/local/cuda/lib:
$LD_LIBRARY_PATH"
```

For 64-bit, type (all on one line):

```
setenv LD_LIBRARY_PATH "/usr/local/cuda/lib64:
$LD_LIBRARY_PATH"
```

These commands set the environment variables **only for the terminal you are in and **only** for your account. To set them permanently, you will need to add it to ~/.cshrc (or similar) file.

To set library path system-wide

CONSULT YOUR SYSTEM ADMINISTRATOR BEFORE CONTINUING

- 1. You will still need to set your PATH as above.
- 2. Depending on whether you use 32-bit or 64-bit Linux, have your system administrator include one of the following paths in /etc/ld.so.conf (or equivalent type file) in the list of directories:

For 32-bit: /usr/local/cuda/lib

For 64-bit: /usr/local/cuda/lib64

3. Then, type as superuser/root:

ldconfig

- Run the CUDA SDK installation script as a **regular user**.
- 4. To verify that you've installed things correctly, run a sample program available with the SDK code samples.
 - a. Within the terminal window, navigate to the location to compile the code samples. If you installed everything in the default directories, then you would type (default directory is only valid for version 2.3):

cd \$HOME/NVIDIA_GPU_Computing_SDK/C

b. Compile the test programs by typing:

make

c. Navigate to the location of the compiled programs by typing (directory is only valid for version 2.3):

```
cd $HOME/NVIDIA_GPU_Computing_SDK/C/bin/linux/release
```

d. Run the deviceQuery program:

```
./deviceQuery
```

If things are running correctly, you will see how many devices are running CUDA (there should be at least 1) and a printout saying that it/they passed the test.

Additional instructions and troubleshooting tips are provided in the "Getting Started" manual on the CUDA download site.

2.2.2 Installing OpenCL

2.2.2.1 Mac OS X

Mac computers with Mac OS 10.6 (Snow Leopard) come with OpenCL installed. OpenCL is not available for earlier versions of Mac OS. If you have Snow Leopard, you already have OpenCL installed. If you don't have Snow Leopard, you must upgrade your operating system to Snow Leopard to get OpenCL.

2.2.2.2 Linux or Windows with NVIDIA GPUs

OpenCL is installed with CUDA on Linux and Windows with NVIDIA GPUs. Follow the instructions in section 2.2.1 to install CUDA if you have an NVIDIA GPU.

2.2.2.3ATI GPUs

Note: This version of Zephyr currently only works under Linux with ATI GPUs. If you have an ATI GPU, install OpenCL by following the instructions at the AMD website http://developer.amd.com/gpu/ATIStreamSDK/Pages/default.aspx.

2.3 Getting OpenMM Zephyr

2.3.1 Download OpenMM Zephyr

OpenMM Zephyr can be freely downloaded from https://simtk.org/home/zephyr. From the main project page, click on the "Downloads" link in the left-hand column (Figure 2.3).

You will be taken to the Downloads webpage. Click on the link for the Zephyr installation for your platform. If you are not already logged in to Simtk.org, you will be asked to log in (or register). You will then be asked to describe how you plan to use this software. Provide a description and then click "Download Now."




Figure 2.3: OpenMM Zephyr can be downloaded from Simtk.org

2.3.2 Install OpenMM Zephyr application

2.3.2.1 Windows

Save the installation program to your computer and then double click to run the installer.

When you install OpenMM Zephyr, you will be asked where to save all the files. You can save the files anywhere you like on your computer. However, **the path name for the installed files must not contain any spaces.** This is a limitation of the version of GROMACS used as the basis for OpenMM Zephyr. For a Windows computer, a good place to save the files is to C:\Zephyr.




Figure 2.4: The Zephyr installer installs some required Microsoft software libraries. Click "Yes" to install these libraries.




Figure 2.5: Sometimes the installation of the Microsoft libraries takes a while. Please be patient.



Installing Zephyr to "My Documents" will not work. You will be able to extract the files to that location but will not be able to run OpenMM Zephyr from there.

Remember: the path for the OpenMM Zephyr files must not contain any spaces.

2.3.2.2 Mac OS

After downloading the dmg installation file, a window should appear instructing you to drag and drop the Zephyr program on the left into your Applications folder (Figure 2.6). If not, locate the dmg file (typically on your Desktop or in your Downloads folder) and double-click on it. Follow the instructions for moving Zephyr into your Applications folder.

This installation also comes with the user manual, ZephyrUserManual.pdf. You should also move this file to a permanent location, e.g., in your Documents folder.

After moving Zephyr and the user manual, you can close the window and delete the .dmg file/eject the disk.




Figure 2.6: The installer for OpenMM Zephyr on Mac OS

2.3.2.3 Linux

After downloading the .sh installation script, open a terminal window and run the script. Follow the on-line directions to complete the installation.

2.3.3 Contents of the OpenMM Zephyr directory

If you have successfully installed OpenMM Zephyr, you should see the following files and directories.

2.3.3.1 Windows

Go to the directory where you installed OpenMM Zephyr (default location is C:\Zephyr). Within that directory, you should see:

- **Zephyr:** This is the OpenMM Zephyr application. Double-click on this to start the program.
- Uninstall: To uninstall OpenMM Zephyr, click on this. The program will be removed from your computer, and all files in the directory except for the testData directory will be deleted.
- **doc:** This directory contains the documentation files
- testData: This directory contains example data files to use for starting the example simulations

You will also see the **bin** directory, which provides files used behind the scenes by the OpenMM Zephyr program, and the COPYING text document that provides the licensing details for OpenMM Zephyr.

2.3.3.2 Mac OS

Go to Macintosh HD -> Applications. Press the ctrl key and click on Zephyr to view the contents. Navigate to Contents -> Resources. You should see a **testData** and a **bin** directory, as well as a COPYING text document that provides the licensing details for OpenMM Zephyr. You will also see Zephyr.icns. The **testData** directory contains example data files to use for starting the example simulations.

2.3.3.3 Linux

Go to the directory where you installed OpenMM Zephyr (default location is /usr/local/zephyr). Within that directory, you should see:

- zephyr: This is the OpenMM Zephyr application. You will run this to start the program.
- **doc:** This directory contains the documentation files
- **testData:** This directory contains example data files to use for starting the example simulations

You will also see the bin directory, which provides files used behind the scenes by the OpenMM Zephyr program, and the COPYING text document that provides the licensing details for OpenMM Zephyr.

3 Running a Simulation

3.1 Launching OpenMM Zephyr

To start OpenMM Zephyr on Windows or Mac OSX, double-click the Zephyr icon. On Linux, go to the directory where you installed Zephyr (the default location is either \$HOME/zephyr/ or /usr/local/zephyr/):

cd \$HOME/zephyr

Then, run zephyr in the background by typing:

./zephyr &

(You can also run Zephyr by double-clicking on the icon in a Linux environment, but in order to get the GPU acceleration, you will need to ask your system administrator to provide system-wide access to the GPU libraries — see Section 2.2 for GPU software installation instructions).

The window shown in Figure 3.2 appears.




Figure 3.1: Launch Zephyr by double clicking the Zephyr icon for Windows or Mac (left: on Windows; right: on Mac OS)



Figure 3.2: OpenMM Zephyr application

Note the series of tabs near the top of the window: Molecules, Parameters, (Idle) (grayed out), VMD console (grayed out), About. The order of the tabs guides you in setting up and running the simulation:

- 1. Choose a molecule to simulate (the Molecules tab) See Section 3.2
- 2. Set the simulation parameters (the Parameters tab) See Section 3.4
- 3. Run the simulation (simulation progress shown in the third tab) See Section 3.5
- 4. If desired, visualize the simulation results in VMD (the VMD tab) See Section 3.7.

You can also use OpenMM Zephyr to continue or extend a simulation run (see Section 3.11) and modify simulation parameters besides the basic ones displayed in the Parameters tab (see Section 3.10).

3.2 Choosing a Molecule

Molecular simulations need an initial molecular structure to start the simulation. OpenMM Zephyr is able to read in structures that are in the Protein Data Bank (PDB) format. See section 3.2.1 for more information about PDB files.

To choose the molecule you wish to simulate, click on the **Molecules** tab. Click the **Browse molecule (PDB) files...** button in the **Initial molecule(s)** panel to select the file describing the molecular structure. You can also type in the file name.

Note: On the Mac OS, Applications/Zephyr.app is recognized as an application, not a folder, so you will not be able to directly access its contents when navigating to it from the Applications folder. This is a problem if you want to access the example PDB files provided by OpenMM Zephyr.

To get to the Zephyr.app sub-folders, go to the Applications folder. Click command—shift—G. A pop-up appears asking for a folder name. Type Zephyr.app. That will take you into the Zephyr.app folder. Navigate to Contents -> Resources -> testData to find example PDB files to use.

3.2.1 PDB files

The Protein Data Bank (PDB) format provides a standard representation for macromolecular structure data derived from X-ray diffraction and NMR studies. This format was created in the 1970s and includes information about the molecule, such as its name, the primary and secondary structure information, and details about how the data was collected.

3.2.1.1 Finding PDB molecular structure files

PDB files can be downloaded from http://www.rcsb.org/pdb/home/home.do, but they might need to be modified to be used by OpenMM Zephyr.

3.2.2 Preparing a PDB file for loading into OpenMM Zephyr

Beginning with Zephyr version 0.9.2, PDB residue and atom names are automatically transformed to be compatible with the ffamber ("amber force field for gromacs": Amber96, Amber99sb, and Amber03) force fields used in Zephyr. If you are running an older version of Zephyr, consult Appendix B for details on manually editing your PDB file for use in Zephyr.

Zephyr version 0.9.2 and later performs the following operations on your input PDB file:

- Renames residues and atoms to be compatible with the ffamber ("amber force fields for gromacs": Amber96, Amber99sb, and Amber03) force fields. This renaming includes special rules for the first and last residues in a chain of protein or RNA.
- Removes water molecules. New water molecules will be added automatically if you perform an explicit solvent simulation in Zephyr.
- Removes certain atoms that are not supported in the ffamber force field, including phosphate atoms at the 5' end of an RNA molecule.

However, additional modifications may be needed in order to use your PDB file with Zephyr. See Appendix B for full details. Some of the more common changes include:

- Modifying or deleting non-standard amino acids and nucleotide residues
- Filling in missing atoms

Note that hydrogen atoms are automatically added to the molecular structure by Zephyr, so hydrogens do not need to be defined in the PDB file. In fact, if any hydrogen atoms are included in the PDB file, they are first removed and then added back in by Zephyr.

The modified PDB file generated and used by Zephyr for running the simulation is saved in the file <input_file_root_name>_processed.pdb in the output directory (see Section 3.3).

3.3 Select Location for Output Files

To select the location for the simulation output files, click on the **Molecules** tab. Click the **Browse folders...** button in the panel for **Output folder** to select the folder for the output files. You can also type in the name of the folder. A default folder for the simulation output files has been created under *C:/Documents and Settings/<User Name>* on Windows, */Users/<User Name>* on Mac OS, <home directory>/simulations on Linux.

3.3.1 What files are saved for a simulation?

Molecular simulations produce what are called "molecular trajectories" or just "trajectories." By definition, a trajectory is the path of a moving body through space. However, in a molecular simulation, many bodies (atoms) are moving through space, so an

intuitive way to capture all the information is to save snapshots of the molecule throughout the simulation. At the end of a simulation, you have information about the molecule (e.g., coordinates of atoms, velocities, etc.) at different time points along the molecular trajectory.

For each simulation, OpenMM Zephyr saves the trajectory information in a .trr file. This is a binary format, so you cannot look at the contents by just opening the file with a text editor. These .trr trajectory files can be viewed in VMD, but only after loading a structure file (.pdb or .gro) containing the molecule.

A number of other files are also saved automatically with each simulation (See Section 3.8.1). These are used by GROMACS to run the simulation and could be used as a starting point to run simulations with GROMACS parameters not provided via the OpenMM Zephyr interface (See Chapter 5). The updated PDB file that Zephyr generates in order to be compatible with the ffamber ("amber force fields for gromacs": Amber96, Amber99sb, and Amber03) force fields naming convention (See Section 3.2.2) is also saved.

If you choose to watch your simulation as it runs, the simulation results will be sent to VMD. VMD provides a variety of options for viewing the simulation, and it allows you to save the trajectory information in a variety of file formats (See Section 3.8.1).

3.4 Parameters

A small subset of all the parameters within GROMACS is available through OpenMM Zephyr. These can be set by clicking on the **Parameters** tab. Within the Parameters view, you can also choose the hardware on which you run your simulation (CPU or GPU) and the VMD options for visualizing the simulation as it runs.




Figure 3.3: Parameters panel

3.4.1 Minimizing energy before dynamic simulation

Sometimes the starting configuration of a molecule in a PDB can have a few close atom contacts or other situation that results in a large calculated potential energy. This situation can cause the simulation to "blow up," in which case the molecular configuration becomes nonsense. It is a good idea to adjust the initial structure by energy minimization to prevent blowing up. This option can be enabled by checking the box for **Minimize** within the **Minimize energy first?** panel within the **Parameters** view. More details about this minimization process can be found by examining the file "testData/em.mdp" and consulting the GROMACS documentation.

3.4.2 Choosing the length of time of your simulation

To set the length of time to run your simulation, click on the **Parameters** tab and use the pull-down menus within the **How long to simulate** panel (located at the top of **Figure 3.3**) You can choose to set the length of time of your simulation (ps = picoseconds = 10^{-12} seconds) or the number of timesteps (steps). The number of timesteps, combined with the timestep interval (ps/step), determines the total simulation time.

The three pull-down menus (ps, steps, and ps/steps) are linked, so changing one will affect the other values. For example, if you have chosen 0.002 ps/step, then running a simulation for 10.0 ps is equivalent to running it for 5000 steps.

3.4.2.1 Guidelines for choosing the total simulation time

When setting up a simulation, you need to decide how long you are willing to wait for a simulation versus what interesting or useful biology can be observed within a given simulation time.

Proteins fold in microseconds to hours. A folding simulation has to calculate new velocities and positions for each atom every couple of femtoseconds. So to compute 1 microsecond (μ s) of actual folding requires 500,000,000 timesteps (assuming a timestep of 2 femtoseconds). The computational time to simulate this many timesteps is staggering. Even with GPUs, simulations are able to compute less than one microsecond per day.

Although the largest values in the simulation time pull-down in Zephyr are 10000 ps (10 ns) and 100000 steps, you can create a longer simulation by typing a larger number into the box. Be aware that such simulations may take a long time, even on a GPU.

Some factors that affect the time needed to simulate one timestep (and thus the total simulation time) include:

- Molecule size: A larger molecule takes longer to simulate than a smaller one
- Hardware: GPU simulations should be faster than CPU simulations
- Frequency of updates to VMD and trajectory file: Sending coordinates less often to VMD and the output trajectory file can result in a faster simulation.

3.4.2.2 Choosing the timestep size

The timestep size needs to be smaller than the fastest phenomenon being simulated in order to accurately simulate it. For molecules, this means the timestep is on the order of a femtosecond (10-15 seconds or 10-3 picoseconds) to account for the fast bond stretch vibrations in the system. However, the smaller the timestep is, the longer the simulation will take to run. If the time step size is too large, the simulation may become unstable and the molecular structure can diverge to an unreasonable configuration. The technical term for this phenomenon is "blowing up."

3.4.3 Setting the temperature for your simulation

The **Temperature** panel within the **Parameters** view allows you to set the temperature of your simulation. You can set the temperature in either Celsius (°C), Kelvin (K), or Fahrenheit (°F) by typing in the value or using the pull-down menus. The left-most pull-down menu within the **Temperature** panel allows you to select from some commonly used temperatures (e.g., freezing temperature, boiling temperature, human body temperature).

3.4.4 Choosing a force field for your simulation

A force field determines how the particles within your simulation will interact. More specifically, it refers to the equations and parameters that describe the potential energy of a system of particles as a function of the particles' positions. There are many different force fields that have been developed for molecular dynamics simulations. They are empirical models, attempts to reproduce what has been observed experimentally, and include approximations to simplify the calculations.

The current version of OpenMM Zephyr includes the Amber96, Amber99sb, and Amber03 force fields. These are classical force fields, meaning they treat each atom as a single particle and models their behavior using Newton's equation of motion (F=ma, where F=force, m=mass, a=acceleration). The forces are specified via potential energy functions that define the interactions between atoms (i.e., bonds, Van der Waals, electrostatic, etc.). These potential energy functions are empirically derived and are what distinguish one force

field from another. You can read more about the Amber force fields in (Ponder & Case, 2003) and (Case, et al, 2005).

The force field is set using the pull-down menu in the **Force field** panel within the **Parameters** view.

3.4.5 Choosing the simulation hardware

Use the pull-down menu for **Simulation hardware** within the **Parameters** view to choose what hardware to use to run your simulation:

Automatic

This is the default option. It uses whatever hardware platform OpenMM determines to be the fastest available. This is a feature of OpenMM and is not specific to Zephyr. If the CUDA platform is available on your computer, CUDA will be chosen because that is judged by the OpenMM selection algorithm to be the fastest platform. Otherwise, if OpenCL is available, OpenCL will be chosen. Finally, if no other platform is available, the Reference (CPU) platform will be used.

Note for those running on ATI GPUs on Windows: The OpenCL platform currently only works correctly on ATI GPUs on Linux (and not on Windows). So, on Windows computers with an ATI GPU and the ATI stream SDK installed, we recommend you select the Reference (CPU) platform manually, rather than use the "Automatic" option.

Reference (CPU)

Simulation runs on your CPU using the OpenMM reference code. Don't expect this mode to be fast. The OpenMM CPU reference code is written for expository pedagogical purposes at the expense of efficiency.

non-OpenMM gromacs

USE FOR TESTING ONLY - This uses standard GROMACS simulation without OpenMM. Beware that this version of GROMACS ignores implicit solvent information, so extreme caution is advised.

CUDA (nVidia GPU)

Simulation runs on your NVIDIA GPU card. If you do not actually have an NVIDIA GPU card, the simulation defaults to the Reference (CPU) option. If you have an NVIDIA GPU card but have not correctly installed the GPU software (see Section 2.2), the simulation will start and then immediately end.

OpenCL (GPU)

Simulation runs on your NVIDIA or ATI GPU card. If you do not actually have a supported GPU card, the simulation defaults to the Reference (CPU) option. If you have a GPU card but have not correctly installed the GPU software (see Section 2.2), the simulation will start and then immediately end.

Note for those running on ATI GPUs on Windows: The OpenCL platform currently only works correctly on ATI GPUs on Linux (and not on Windows). So, on Windows computers with an ATI GPU and the ATI stream SDK installed, you need to select the Reference (CPU) platform.



Use the non-OpenMM gromacs option for testing purposes only. The version of (non-OpenMM) GROMACS used by Zephyr ignores implicit solvent information, so the simulation results may not make any sense.

3.4.6 Solvent collision interval

The solvent collision interval specifies the average time it takes a solvent molecule to collide with another solvent molecule (in ps). For instance, the experimental value for water is 0.01099 ps. This number provides a measure of the solvent viscosity. A higher value means that there will be longer time gaps between solvent collisions, which means you have a less viscous solvent. A molecule in a less viscous solvent can move more easily and thus will fold faster (Zagrovic & Pande, 2003).

To set this value, use the pull-down menus in the Solvent collision interval panel within the **Parameters** view. Currently, you can choose between an "accurate water" collision interval of 0.01099 ps and the "faster dynamics" time interval of 1.0 ps. This setting corresponds to the tau_t parameter setting in GROMACS' parameters file (see Chapter 5).

3.4.7 Live viewing in VMD

You can watch the simulation as it is running by checking the box for View simulation live in VMD within the Parameters view. Set the frequency at which VMD is updated with the simulation output using the pull-down menu for **ps** or **steps** within the **Output frequency** panel.

If the simulation appears jerky and/or updates very slowly, try increasing the frequency at which information is sent to VMD. However, increasing the frequency (decreasing the number of timesteps or the time period) will also cause your simulation to run slower.

Viewing your simulation in VMD will slow it down. You can minimize the impact of the live viewing by increasing the time period (or the number of steps) for sending information over to VMD.

3.4.8 Saving trajectory frames

Choose the frequency at which the trajectory frames from your simulation are saved by using the pull-down menus for **ps** or **steps** in the **Output frequency** panel within the **Parameters** view. Be aware that saving frames frequently can slow down the simulation, especially with GPU accelerated simulations.

3.4.9 Explicit solvent vs. implicit solvent

Zephyr simulates macromolecules using an implicit solvent model by default. An implicit solvent model provides a mathematical representation of the solvent effects, rather than modeling the individual solvent molecules, and results in a faster simulation. To use explicit solvent, check the **Use Explicit Solvent** check box. This will cause individual water molecules and salt ions to be added to the simulation. Checking the **Use Explicit Solvent** box applies changes to several parameters, including the force field and the integration method. The size of the simulation box is chosen to be somewhat larger than the size of the molecule being simulated. Salt (sodium chloride) ions are added to neutralize the total charge of the system, and to match the ionic strength of human tissue fluid. Water molecules are added to fill the simulation box. A barostat is used to adjust the box size during simulation to maintain atmospheric pressure.

3.5 Starting a Simulation

Once you have specified the molecule you wish to simulate and chosen the simulation parameters, you can start the simulation by clicking the **Simulate** button in the lower-right corner of the **Parameters** view. OpenMM Zephyr will automatically switch to the **Status** view (third tab). This view provides information about how much of the simulation has been completed. It also shows you the output from GROMACS, the underlying molecular

dynamics simulation, in black in the **gromacs output** panel. Items in blue in this panel are either commands sent from Zephyr to GROMACS or status messages.




Figure 3.4: View when a simulation is running

If you chose to view the simulation as it was running (See Section 3.4.6), two VMD windows should appear, one of which shows the molecule (Figure 3.5). You may get security alert message(s), as shown in Figure 3.6. If so, just click **Unblock** to allow OpenMM Zephyr to communicate with VMD.




Figure 3.5: VMD can be used to watch the simulation as it runs




Figure 3.6: Click "Unblock" to grant permission for Zephyr and VMD to communicate through TCP sockets

3.6 Restrictions on Simulations in Zephyr

3.6.1 Amber Force Fields

Only Amber force fields (Amber96, Amber99sb, Amber03) are available from the Zephyr interface. Use of other force fields may be possible from the command line (see Chapter 5), and may require different conventions for the naming of atom and residue types.

3.7 VMD Console

The VMD console tab provides an interface between OpenMM Zephyr and VMD. VMD commands sent by OpenMM Zephyr (shown in blue), as well as VMD output (shown in black) are displayed. There is also a field at the top (**Type VMD commands here**) to type in commands and control VMD via the command line. See the VMD User's Guide for more information: http://www.ks.uiuc.edu/Research/vmd/current/ug/.




Figure 3.7: VMD console

3.8 Final Simulation Results

The trajectory produced by the simulation is saved by OpenMM Zephyr and can be loaded into VMD for viewing and additional processing (See Section 3.8.1). OpenMM Zephyr also saves other intermediate files used by the simulation (See Section 3.8.2).

3.8.1 Saving a trajectory from VMD

Once your trajectory is loaded into VMD, you can save trajectory and structure files in many file formats from within VMD. These and many other rich features of the VMD

program are documented in the current version of the VMD User's Guide, available at http://www.ks.uiuc.edu/Research/vmd/current/ug/.

3.8.2 Contents of simulation output directory

GROMACS-OpenMM, upon which OpenMM Zephyr is built, produces a number of files during the simulation. These are like the standard files produced by GROMACS but they cannot be used with GROMACS, only with the OpenMM version of GROMACS. A partial list of these files is given below.

For a more complete description of the files, refer to the documentation for GROMACS 4.0 (http://www.gromacs.org/component/option.com_wrapper/Itemid,192/). The links to the Flow Chart and to Getting Started -> GROMACS files may be particularly useful.

md.out.(mdp) This is an MDP file (the mdp extension may or may not appear, depending on your browser settings). It is the input parameters file for the simulation, containing information such as how long to run the simulation, the timestep, and the temperature for the simulation.

This file contains the trajectory of the simulation. It will include the coordinates and velocities. This is in a binary format, so it cannot be read using a regular text editor but it can be viewed using VMD.

md(.log) This text file is the GROMACS-OpenMM log file for the simulation. The information is what GROMACS outputs, which is a subset of the text printed in the **gromacs output** panel of the **Status** view.

.tpr file

This file contains the starting structure of your simulation, the molecular topology, and all the simulation parameters. It is generated by several pre-processing steps and is in a binary format, so it cannot be read using a regular text editor.

OpenMM Zephyr also outputs **zephyr.log**, a text file that captures the output shown in the **gromacs output** panel of the **Status** view, including the Zephyr commands used to interface with GROMACS.

3.8.2.1 Cleaning up when the output directory gets too full

After you have run a very large number of simulations in the same directory, your simulations may stop working. Try removing backup files in the directory, i.e., those with names beginning with a '#' character. To avoid this problem (and keep better track of your simulations), you may want to use a separate directory for each new simulation.

3.9 Stopping a Simulation

Press the **Cancel** button in the **Status** panel to halt a running simulation.

3.10 Modifying Parameters Not Shown in the OpenMM Zephyr GUI (advanced)

OpenMM Zephyr uses a modified version of GROMACS (GROMACS-OpenMM) to run molecular simulations. Power users who are familiar with GROMACS may be able to run a wider variety of simulations using the command line. See Chapter 5 for a brief tutorial on how to run GROMACS-OpenMM from the command line. The GROMACS user documentation at http://www.gromacs.org/ may also be helpful.

Many of the simulation parameters supported by OpenMM Zephyr are available from the **Advanced Parameters...** button within the **Parameters** panel.

3.11 Continuing a Previous Simulation

It is possible to pick up where a previous trajectory left off in OpenMM Zephyr. This feature is available since Zephyr version 1.1. Within the **Molecules** panel is a section called **Continue a previous run**. Select a trajectory file (.trr) from your previous run and press the **Continue simulation** button to continue the run.

3.11.1.1 Extending your current simulation

To continue a successfully completed run in the same Zephyr session:

- 1. Click on the **Molecules** tab
- 2. Verify that the latest trajectory file is listed in the **Continue a previous run** field. (The correct file should be there automatically.)

- 3. Verify that the **Auto load mdp params** box is checked.
- Enter the number of picoseconds you wish to add to the simulation in the Extend time by box.
- 5. Press **Continue simulation**. This will create a new trajectory file, which picks up where the previous trajectory left off.

3.11.1.2 Extending your current simulation with changes

If you want to change parameters in the continued simulation, the procedure is a bit more complicated. You can, for example, enable or disable VMD visualization, or change the viscosity of the simulation before continuing.

- 1. Click on the **Molecules** tab
- 2. Verify that the latest trajectory file is listed in the **Continue a previous run** field.
- Press Load mdp now. This will load the simulation parameters associated with the previous trajectory. The Auto load mdp params box should now be automatically UNchecked.
- 4. Click on the **Parameters** tab and adjust the parameters as desired.
- 5. Return to the **Molecules** panel.
- Enter the number of picoseconds you wish to add to the simulation in the Extend time by box.
- 7. Press **Continue simulation**. This will create a new trajectory file.

3.11.1.3 Extending a simulation from a previous Zephyr session

- 1. Click on the **Molecules** tab
- 2. Press the ... button under the **Continue a previous run** section. This launches a file browser. Load the trajectory file (.trr) that you want to continue from.
- 3. Verify that the **Auto load mdp params** box is checked.
- Enter the number of picoseconds you wish to add to the simulation in the **Extend** time by box.

5. Press **Continue simulation**. This will create a new trajectory file, which picks up where the previous trajectory left off.

3.11.1.4 Continuing a cancelled or crashed trajectory

This method can also be used to continue a run that has been terminated, though it does not work well yet.

- 1. Click on the **Molecules** tab
- 2. Press the ... button under the **Continue a previous run** section. This launches a file browser. Load the trajectory file (.trr) that you want to continue from.
- Press Load mdp now. This will load the simulation parameters associated with the previous trajectory. The Auto load mdp params box should now be automatically UNchecked.
- 4. Set the **Extend time by** field to a small value, such as 1.0 picoseconds.
- 5. In the **Parameters** panel, set **How long to simulate** to a small number of **steps**, such as 1 step.
- 6. Return to the **Molecules** panel.
- 7. Press **Continue simulation**. This will create a new trajectory file, which picks up where the previous trajectory left off.

4 Troubleshooting

4.1 Why is my simulation updating in VMD so slowly?

If the VMD view of the simulation is changing very slowly, try decreasing the interval for VMD updates, and restarting the simulation. This will result in a smoother display in the VMD window. This may however also result in a longer running time.

4.2 I am getting the message "Waiting for IMD socket connection to VMD on port 3000"

Click to the VMD console view to see what is happening with VMD. Depending on the message you see, you will need to take different actions:

VMD console message/issue	<u>Action</u>					
couldn't open socket: address already in use	Cancel the simulation by clicking the Cancel					
	button in the Status view.					
	Close the VMD windows that appeared.					
	Click the Parameters tab.					
	Change the values of Socket for coordinates and for commands (See Section 3.4.6)					
VMD appears to have hung	Scroll up through the list of VMD commands and outputs, and locate the command "imd connect"					

Copy and paste the command in quotes in the

field for VMD commands.

4.3 The "Simulation complete" message appears but the "Elapsed lab time" does not stop

The simulation is completed when the message appears. However, there are other tasks, such as writing out the files, that are being performed and are included in the calculation of the **Elapsed lab time**. So the **Elapsed lab time** will stop when all tasks are done.

4.4 I cannot see the full Zephyr screen and am unable to resize the window on the Mac.

Due to screen resolutions, the Zephyr window may extend beyond the bottom of your screen upon launching. On Macintosh computers, this presents a problem since the location of the resize function is in the lower-right corner of the window and is not accessible. To make the Zephyr window the size you want it to be, first click the button to maximize the window. Then you will be able to resize it to the desired size.

5 Going Further: Running GROMACS-OpenMM from the Command Line

5.1 Generating Initial Parameter and Simulation Input Files

You can use OpenMM Zephyr to generate initial parameter files for your simulation. You can then modify these files to run simulations using parameters that are not accessible through the OpenMM Zephyr GUI or to continue a simulation you started with Zephyr.

- 1) Create a new folder named "testRun" to save the results of your command line Gromacs-OpenMM run. Be sure to remember the full path to testRun. You will need it later.
- 2) Locate your Zephyr install (on Windows, this is typically C:\Zephyr; on Mac OS, this is typically in the Applications folder (/Applications))
- 3) Launch Zephyr
 - a) Select the **Initial molecule** of your choice
 - b) Set the **Output folder** to the testRun directory created earlier
 - c) Click on **Parameters**. You will run Zephyr to get initial parameter and simulation input files and to minimize the energy of your structure before the simulation. Suggested initial parameters are as follows (see Figure 5.1 below):
 - a. Set the length of the simulation time to 0.1 ps
 - b. Make sure the **Minimize energy first?** box is checked
 - c. Uncheck View simulation live in VMD
 - d) Select the **Simulate** button

The run should finish very quickly.




Figure 5.1: Suggested parameter settings to generate initial files to run a GROMACS simulation

5.2 Preparing for a Command Line mdrun_openmm

mdrun_openmm is the command to actually start the simulation. There are a few more steps that you need to take before you are ready to start the simulation.

- 1) Verify the content of your testRun folder. Zephyr should have added the files shown below in Figure 5-2 to your folder (files starting with '#' are not shown). Note the molecule name in the example below was "villin."
- 2) Locate the following files:
 - a. $md.out.mdp \rightarrow this$ is the parameter file (it may be listed as md.out if your settings are set to not show extensions)

- b. villin_processed.box.em.gro [with "villin" replaced by your molecule name]
- c. villin_processed.top [with "villin" replaced by your molecule name]

```
em.out.mdp
ener.edr
md.log
md.out.mdp
posre.itp
state.cpt
traj.trr
villin_processed.box.em.gro
villin processed.box.em.md.gro
villin_processed.box.em.md.mdp
villin_processed.box.em.md.tpr
villin processed.box.em.md.trr
villin_processed.box.em.tpr
villin_processed.box.gro
villin_processed.gro
villin_processed.top
zephyr.log
```

Figure 5.2: Content of testRun directory after initial Zephyr run (files starting with # were omitted). Note the molecule name in this example was "villin."

3) Edit the md.out.mdp file to change parameters. Save the edited file to a new name, e.g., villinMod.mdp.

You definitely want to set *nsteps* to at least 10000 to get a trajectory (.trr file) with a few frames. Consult the GROMACS documentation (http://www.gromacs.org) for details on other variables. Note that only some of the options have been implemented.

To run a GROMACS simulation, you will first have to run grompp on your modified .mdp file and then mdrun_openmm (details in Section 0 below).

4) Get the terminal window, environment variables and paths ready




Figure 5.3: Windows users: Paste commands into your **Command Prompt window** by right-mouse clicking the top blue bar and selecting Edit→ Paste.

Instructions for Windows

Open a command prompt by selecting

Start → All Programs → Accessories → Command Prompt

cd to the testRun directory created earlier that has the Zephyr output files.

Set environment and PATH variables so that the program knows where to find the program files it needs. See Figure 5.3 for copy/paste instructions into the command prompt window.

set GMXLIB=c:\Zephyr\bin\gmxlib

PATH=c:\Zephyr\bin\win32; %PATH%

Type set (to verify that GMXLIB is defined correctly)

Type path (to verify that your path contains c:\Zephyr\bin\win32)

To set these permanently do the following:

Go to Start → Control Panel → System → Advanced → Environment variables Under "User Variables for xxx" select "New"

Set Variable Name: GMXLIB

Set Variable Value: C:\Zephyr\bin\gmxlib

For GPU acceleration, you need to set and verify the <code>OPENMM_PLUGIN_DIR</code> following the same directions above as for setting and verifying <code>GMXLIB</code>.

To execute on an NVIDIA GPU, add:

set OPENMM_PLUGIN_DIR=c:\Zephyr\bin\win32\lib\openmm\nvidia

Instructions for Mac OS

Open a terminal window

cd to the testRun directory created earlier that has the Zephyr output files

Set environment and PATH variables so that the program knows where to find the program files it needs.

export GMXLIB=/Applications/Zephyr.app/Contents/Resources/bin/gmxlib

export

PATH=\$PATH:/Applications/Zephyr.app/Contents/Resources/bin/mac

export DYLD_LIBRARY_PATH=/Applications/Zephyr.app/Contents/Resources /bin/mac: \$DYLD_LIBRARY_PATH

Type printenv (to verify variables and path settings)

To set these variables permanently, do the following:

echo 'export GMXLIB=/Applications/Zephyr.app/Contents/Resources/bin/ gmxlib' >> ~/.bash_profile

echo 'export PATH=\$PATH:/Applications/Zephyr.app/Contents/Resources/ bin/mac' >> ~/.bash_profile

echo 'export DYLD_LIBRARY_PATH=/Applications/Zephyr.app/Contents/Res ources/bin/mac' >> ~/.bash profile

For GPU acceleration, you need to set and verify the OPENMM PLUGIN DIR following the same directions above as for setting and verifying GMXLIB.

To execute on an **NVIDIA GPU**, add:

export OPENMM_PLUGIN_DIR=/Applications/Zephyr.app/Contents/Resources /bin/mac/lib/openmm/nvidia

5.3 Ready to Run

Once your paths are set, you are ready to run GROMACS from the command line. The first step is to run grompp, the GROMACS preprocessor that will produce a .tpr file, which has all the information for your simulation.

- Run grompp. For more information, consult http://www.gromacs.org/ and search for grompp.
 - ➤ Paste the command below (after replacing "villin" with your molecule name) in your command prompt window (see also SUGGESTION below):

```
grompp -f villinMod.mdp -c villin_processed.box.em.gro -p
villin_processed.top -o villinMod.tpr
```

Replace villinMod.mdp with whatever file name you used for your edited md.out.mdp file.

SUGGESTION: Copy the commands into a text file. Replace "villin" with your molecule name, and then copy and paste the commands from there. Note for Window users: see Figure 5.3 for copy/paste commands; you can also copy the above command into a ".bat" file (e.g., gromppRun.bat) and simply type gromppRun.bat into the command prompt window.

- 2) You are now ready to run mdrun_openmm and start your simulation.
 - ➤ Paste the command below into the command prompt window (after replacing "villin" with your molecule name) or follow the "shortcut" instructions below:

```
mdrun openmm -s villinMod.tpr -o villinMod.trr -c villinMod.gro
```

This creates a new .trr (trajectory) file.

> Shortcut:

Note that "villinMod" is repeated many times in the above command. To avoid retyping this "prefix," GROMACS allows you to execute the shorter equivalent command:

```
mdrun_openmm -deffnm villinMod
```

5.4 Restarting a Simulation that Finished Running in Zephyr

To restart a simulation that terminated in Zephyr, follow similar steps as before. Note: you can skip steps 1 & 2 if you are continuing with the same parameters and VMD was off during that run.

1) Edit the md.out.mdp file and save the edits to a new file villinRestart.mdp

This is only needed if you need to make changes to the parameter file, for example turning off VMD. You will also typically want to increase the total number of steps in the simulation, but you can also do this in step 3. If *nsteps* was 10000 and you would like to perform another 5000 steps, you would set *nsteps* to 15000 either in your .mdp file or in step 3.

2) Run grompp as before:

```
grompp -f villinRestart.mdp -c villin_processed.box.em.gro -pvillin_processed.top -ovillin_temp.tpr
```

3) Run tpbconv, which will modify the .tpr file (input is villintemp.tpr; output is villinRestart.tpr) to continue the simulation from the last frame of the .trr file:

```
tpbconv -s villintemp.tpr -f villin_processed.box.em.md.trr
-nsteps 15000 -o villinRestart.tpr
```

4) Run mdrun_openmm (we recommend appending "part2" to the name of the new output trajectory):

```
mdrun_openmm -s villinRestart.tpr -o villin.part2.trr
```

5.5 Visualizing Your Trajectory in VMD

After the completion of mdrun_openmm, you can visualize the resulting trajectory in VMD using the .trr and .gro files as follows:

1) Start VMD:

Windows: **Start** -> **All Programs** -> **University of Illinois** -> **VMD** -> **VMD X.X.X** (where X.X.X. refers to the version number)

Mac: go to your Applications folder and double click VMD

2) In the VMD Main window, select **File** → **New Molecule**

a. Enter Filename.

Browse to the testRun directory and select villin_processed.box.em.md.trr, where "villin" is replaced by your molecule name.

b. Hit Load. Do NOT close the window.

c. Enter Filename.

Browse to the testRun directory and select villin_processed.box.em.gro, where "villin" is replaced by your molecule name.

d. Hit Load

You can now "play back" your trajectory.

See http://www.ks.uiuc.edu/Research/vmd/current/docs.html#tutorials for a complete set of options in VMD.

6 Giving Back: SubmittingBug Reports and FeatureRequests

Feedback about OpenMM Zephyr is very much appreciated. Please submit bug reports and feature requests on-line at http://simtk.org/home/zephyr. Click on Advanced -> Features & Bugs -> Submit New.




Figure 6.1: Investigate, submit, or track feature requests and bug reports at Simtk.org

7 Appendix A: GROMACS-OpenMM Limitations

Only a fraction of the features of Gromacs 4 are supported in this release of Gromacs-OpenMM. Here are some of the most significant limitations to the allowed options in the MDP file.

The only supported integrators are "md", "sd", and "bd".

The only supported settings for the "constraints" options are "none", "hbonds", or "all-bonds".

The only supported settings for "coulombtype" are "Reaction-Field", "Ewald", and "PME". If you specify any other value, then no cut-offs will be applied.

The only supported thermostat is the Andersen thermostat. Gromacs 4 does not natively use the the Andersen thermostat. Setting the "tcoupl" setting to any of "vrescale", "berendsen", "nosehoover", "andersen", or "yes" will cause the Andersen thermostat to be used. Temperature coupling can also be achieved by using the "sd" or "bd" integrator.

The only supported barostat is the Monte Carlo barostat. Gromacs 4 does not natively use the Monte Carlo barostat. Setting the "pcoupl" setting to any of "berendsen", "isotropic" or "parrinellorahman" will cause the Monte Carlo barostat to be used. Parameters "tau_p", "ref_p", and "ref_t" are used by the Monte Carlo barostat, but the "compressibility" parameter is not used.

Virtual interaction sites are not supported.

54 APPENDIX A: GROMACS-OPENMM LIMITATIONS

Gromacs-OpenMM supports implicit solvent, even though this is not available in the standard Gromacs 4. Implicit solvent can be added to a simulation by including the following three lines in the MDP file.

```
implicit_solvent = GBSA
gb_algorithm = OBC
gb_epsilon_solvent = 78.3
```

By default, implicit solvent only works with the AMBER99 force field. To use it with other force fields, you must add the appropriate atom types to the params.agb file.

Only isotropic position restaint is supported. The force parameters in the x, y, and z directions must be equal.

8 Appendix B: ffamber (Amber96) PDB Naming Conventions

Versions of Zephyr prior to version 0.9.2 require you to modify your input PDB file. In order to be compatible with the force field used in the OpenMM Zephyr simulations (GROMACS AMBER-96), you will need to edit the PDB file. See http://chemistry.csulb.edu/ffamber/ for complete details.

Note that hydrogen atoms are automatically added to the molecular structure by Zephyr, so hydrogens do not need to be defined in the PDB file. In fact, if any hydrogen atoms are included in the PDB file, they are first removed and then added back in by Zephyr.

Use a text editor (*not* Microsoft Word) or write a script to make the changes to residue and atom names, described below.

8.1.1.1 PDB residue names

Residue names are three characters long (including spaces) and are found in columns 18 to 20 of PDB "ATOM" and "HETATM" lines. More details of the PDB file format specification can be found at http://www.wwpdb.org/documentation/format23/sect9.html.

ATOM	759	C4	U N	40	1.034	5.731	-3.177	1.00	0.00	С
ATOM	23	CA	SER	2	16.690	28.620	35.070	1.00	0.00	C
					333333333					
1234567	789012	3456	7 <mark>890</mark> 12	3456789	0123456789	01234567	89012345	678901	2345678901	.23456789

Figure 8.1: Standard PDB residue name format for RNA and protein in columns 18-20. Column numbers are shown vertically in black.


Sometimes you will need to insert a four character residue name (see below). In these cases, you may use the otherwise unused 21st column for the fourth character of the residue name.

8.1.1.2 PDB atom names

Atom names are four characters long (including spaces), and are found in columns 13 to 16 of PDB "ATOM" and "HETATM" lines. The two left-most characters of the atom name are usually the one- or two-character chemical element symbol for the atom, right-justified. For example the atom name "CA" (space-C-A-space) refers to a carbon atom, with element symbol "C". (A calcium atom, with element symbol "Ca", might also be named "CA", but the "C" and "A" characters would appear in columns 13 and 14 so C-A-space-space).

ATOM	759	C4	U N	40	1.034	5.731	-3.177	1.00	0.00	C
ATOM	23	CA	SER	2	16.690	28.620	35.070	1.00	0.00	C
0000000	00111	1111	1112222	22222	23333333333	4444444	44555555	555566	66666667	777777777
1234567	789012	<mark>3456</mark>	7890123	456789	90123456789	01234567	89012345	678901	234567890	123456789

Figure 8.2: PDB atom name fields are in columns 13-16



8.1.1.3 Remove water, ligands, and other molecules that are not protein, RNA, nor DNA

Water molecules (residue name "HOH") should be removed from PDB files for simulation in Zephyr. Further, other molecule types and atoms that are neither protein nor RNA (specifically, any residue types not defined in the file bin/gmxlib/ffamber96.rtp) should also be removed.

```
HETATM 605 O HOH A 79 6.861 9.897 73.678 1.00 20.00 O
```

Figure 8.3: Example of a water molecule PDB line. Delete this line and others like it.

8.1.1.4 Handling missing atoms

Many molecule structures from the protein data bank (PDB) contain incomplete residues, missing some non-hydrogen atoms. Zephyr does not allow you to simulate molecules with missing atoms, since this would lead to inaccurate simulations. You can try to correct the file by manually adding in the missing atoms or using one of the available programs for constructing molecular models, such as Schrodinger's Maestro or the Sali lab's Modeller, both of which are free for academic users.

8.1.1.5 Proteins: Modifying residue and atom names

Protein residue names CYS, HIS, and LYS must be changed to be consistent with the ffamber force field in GROMACS:

- CYS residue name: Convert to CYN, unless it's in a disulfide bridge, in which case use residue name "CYS2". "CYS2" is an example of a four character residue name that requires using the 21st column of the ATOM line for the fourth character.
- HIS residue name: Convert to HID, HIE, or HIP, depending on whether the residue is be protonated at the delta nitrogen (HID), epsilon nitrogen (HIE), or both (positively charged - HIP). This choice depends on the arrangement of nearby hydrogen bond donors and acceptors.
- LYS residue name: Convert to LYP

ATOM	188	N	CYS A	42	40.714	-5.292	12.123	1.00	11.29	N
ATOM	559	CG	HIS A	90	33.017	-0.052	-3.236	1.00	16.37	С
ATOM	518	CA	LYS A	85	31.348	-0.655	-11.701	1.00	47.73	С
ATOM	188	N	CYN A	42	40.714	-5.292	12.123	1.00	11.29	N
ATOM	559	CG	HID A	90	33.017	-0.052	-3.236	1.00	16.37	С
								1.00		C

Figure 8.4: Example of modifying protein residue names: (top) before editing, (bottom) after editing

8.1.1.5.1 Initial N-terminal amino acid residues

Both the first and the last residue of each continuous protein chain require additional changes to residue and atom names. Initial protein residues (N-terminal residues) must be prefixed with the letter "N". This results in four-character residue names, and thus must make use of the 21st column in the PDB ATOM lines.

ATOM	1	N	HIS A	19	28.165	29.227	23.618	1.00 91.78	N
ATOM	2	CA	HIS A	19	27.004	29.173	22.731	1.00 91.74	C
ATOM	3	C	HIS A	19	26.321	27.818	22.666	1.00 81.05	C
ATOM	4	0	HIS A	19	25.105	27.739	22.805	1.00 89.56	0
ATOM	5	CB	HIS A	19	27.248	29.629	21.270	1.00 98.21	C
ATOM	6	CG	HIS A	19	27.954	30.936	21.082	1.00100.00	C
ATOM	7	ND1	HIS A	19	28.852	31.112	20.015	1.00100.00	N
ATOM	8	CD2	HIS A	19	27.882	32.111	21.798	1.00100.00	C
ATOM	9	CE1	HIS A	19	29.310	32.368	20.116	1.00100.00	C
ATOM	10	NE2	HIS A	19	28.753	32.997	21.176	1.00100.00	N
ATOM	11	N	SER A	20	27.057	26.778	22.303	1.00 58.48	N
3.0016	- 1			1.0	20 165	20 227	22 610	1 00 01 70	27
ATOM	1	N	NHIDA	19	28.165	29.227	23.618	1.00 91.78	N
ATOM	2	CA	NHIDA	19	27.004	29.173	22.731	1.00 91.74	C
ATOM	3	C	NHIDA	19	26.321	27.818	22.666	1.00 81.05	C
ATOM	4	0	NHIDA	19	25.105	27.739	22.805	1.00 89.56	0
ATOM	5	CB	NHIDA	19	27.248	29.629	21.270	1.00 98.21	C
ATOM	6	CG	NHIDA	19	27.954	30.936	21.082	1.00100.00	C
ATOM	7	ND1	NHIDA	19	28.852	31.112	20.015	1.00100.00	N
ATOM	8	CD2	NHIDA	19	27.882	32.111	21.798	1.00100.00	C
ATOM	9	CE1	NHIDA	19	29.310	32.368	20.116	1.00100.00	C
	10	ME 2	NHIDA	19	28.753	32.997	21.176	1.00100.00	N
ATOM	10	1412.5	.,						

Figure 8.5: Example of modifying initial N-terminal amino acid residue names: (top) Initial residue HIS 19 before editing. Notice that the initial residue is not always number "1". (bottom) Initial protein residue after editing. Four character residue name spills into column 21.

8.1.1.5.2 Final C-terminal amino acid residues

C-terminal amino acid residue names must be prefixed with a "C". Again, this will create a four-character residue name that must use column 21 of the ATOM line. Further, for the C-terminal residues only, the atom names "O" and "OXT" must be changed to "OC1" and "OC2", respectively.

ATOM	2339	CG2	VAL A	313	15.802	10.026	10.329	1.00	6.43	C
ATOM	2340	N	TYR A	314	18.123	7.078	9.077	1.00	11.96	N
ATOM	2341	CA	TYR A	314	18.703	6.708	7.797	1.00	13.08	C
ATOM	2342	C	TYR A	314	17.968	5.444	7.240	1.00	12.06	C
ATOM	2343	0	TYR A	314	18.333	5.097	6.066	1.00	21.58	0
ATOM	2344	CB	TYR A	314	20.271	6.496	7.921	1.00	9.89	C
ATOM	2345	CG	TYR A	314	20.564	5.634	9.181	1.00	15.02	C
ATOM	2346	CD1	TYR A	314	20.402	4.250	9.128	1.00	12.83	C
ATOM	2347	CD2	TYR A	314	20.931	6.188	10.414	1.00	14.05	C
ATOM	2348	CE1	TYR A	314	20.671	3.408	10.205	1.00	9.53	C
ATOM	2349	CE2	TYR A	314	21.238	5.367	11.505	1.00	6.19	C
ATOM	2350	CZ	TYR A	314	21.068	3.985	11.411	1.00	10.42	C
ATOM	2351	OH	TYR A	314	21.357	3.139	12.450	1.00	11.71	0
ATOM	2352	OXT	TYR A	314	17.078	4.932	7.946	1.00	17.12	0
TER	2353		TYR A	314						
ATOM	2339	CG2	VAL A	313	15.802	10.026	10.329	1.00	6.43	C
ATOM	2340	N	CTYRA	314	18.123	7.078	9.077	1.00	11.96	N
ATOM	2341	CA	CTYRA	314	18.703	6.708	7.797	1.00	13.08	C
ATOM	2342	C	CTYRA	314	17.968	5.444	7.240	1.00	12.06	C
ATOM	2343	റവ								
ATOM		OCI	CTYRA	314	18.333	5.097	6.066		21.58	0
111 011	2344	CB	CTYRA CTYRA		18.333 20.271					0 C
ATOM	2344 2345			314		5.097	6.066	1.00 1.00	21.58	
		CB CG	CTYRA	314 314	20.271	5.097 6.496	6.066 7.921	1.00 1.00 1.00	21.58 9.89	C C
ATOM	2345	CB CG CD1	CTYRA CTYRA	314 314 314	20.271 20.564	5.097 6.496 5.634	6.066 7.921 9.181	1.00 1.00 1.00 1.00	21.58 9.89 15.02	C C
ATOM ATOM	2345 2346 2347 2348	CB CG CD1 CD2 CE1	CTYRA CTYRA CTYRA CTYRA CTYRA	314 314 314 314 314	20.271 20.564 20.402 20.931 20.671	5.097 6.496 5.634 4.250 6.188 3.408	6.066 7.921 9.181 9.128 10.414 10.205	1.00 1.00 1.00 1.00 1.00	21.58 9.89 15.02 12.83 14.05 9.53	0 0 0 0
ATOM ATOM ATOM	2345 2346 2347	CB CG CD1 CD2 CE1	CTYRA CTYRA CTYRA CTYRA	314 314 314 314 314	20.271 20.564 20.402 20.931	5.097 6.496 5.634 4.250 6.188	6.066 7.921 9.181 9.128 10.414	1.00 1.00 1.00 1.00	21.58 9.89 15.02 12.83 14.05	с с с
ATOM ATOM ATOM	2345 2346 2347 2348	CB CG CD1 CD2 CE1	CTYRA CTYRA CTYRA CTYRA CTYRA	314 314 314 314 314 314	20.271 20.564 20.402 20.931 20.671	5.097 6.496 5.634 4.250 6.188 3.408	6.066 7.921 9.181 9.128 10.414 10.205	1.00 1.00 1.00 1.00 1.00 1.00	21.58 9.89 15.02 12.83 14.05 9.53	0 0 0 0
ATOM ATOM ATOM ATOM	2345 2346 2347 2348 2349	CB CG CD1 CD2 CE1 CE2 CZ OH	CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA	314 314 314 314 314 314 314	20.271 20.564 20.402 20.931 20.671 21.238	5.097 6.496 5.634 4.250 6.188 3.408 5.367	6.066 7.921 9.181 9.128 10.414 10.205 11.505	1.00 1.00 1.00 1.00 1.00 1.00	21.58 9.89 15.02 12.83 14.05 9.53 6.19	0 0 0 0 0
ATOM ATOM ATOM ATOM ATOM	2345 2346 2347 2348 2349 2350	CB CG CD1 CD2 CE1 CE2 CZ OH	CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA	314 314 314 314 314 314 314	20.271 20.564 20.402 20.931 20.671 21.238 21.068	5.097 6.496 5.634 4.250 6.188 3.408 5.367 3.985 3.139	6.066 7.921 9.181 9.128 10.414 10.205 11.505	1.00 1.00 1.00 1.00 1.00 1.00 1.00	21.58 9.89 15.02 12.83 14.05 9.53 6.19 10.42	0 0 0 0 0 0
ATOM ATOM ATOM ATOM ATOM ATOM	2345 2346 2347 2348 2349 2350 2351	CB CG CD1 CD2 CE1 CE2 CZ OH	CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA CTYRA	314 314 314 314 314 314 314 314	20.271 20.564 20.402 20.931 20.671 21.238 21.068 21.357	5.097 6.496 5.634 4.250 6.188 3.408 5.367 3.985 3.139	6.066 7.921 9.181 9.128 10.414 10.205 11.505 11.411 12.450	1.00 1.00 1.00 1.00 1.00 1.00 1.00	21.58 9.89 15.02 12.83 14.05 9.53 6.19 10.42 11.71	
ATOM ATOM ATOM ATOM ATOM ATOM ATOM	2345 2346 2347 2348 2349 2350 2351 2352	CB CG CD1 CD2 CE1 CE2 CZ OH	CTYRA	314 314 314 314 314 314 314 314	20.271 20.564 20.402 20.931 20.671 21.238 21.068 21.357	5.097 6.496 5.634 4.250 6.188 3.408 5.367 3.985 3.139	6.066 7.921 9.181 9.128 10.414 10.205 11.505 11.411 12.450	1.00 1.00 1.00 1.00 1.00 1.00 1.00	21.58 9.89 15.02 12.83 14.05 9.53 6.19 10.42 11.71	

Figure 8.6: Modification of final protein residue name: (top) before editing, (bottom) after editing

8.1.1.6 RNA: Modifying residue and atom names

RNA and DNA molecules from the Protein Data Bank use residue names "A", "C", "G", "T", and "U". These one letter names are found in the right-most of the three residue name character positions (columns 18-20).

- Prefix RNA residue names with an "R", and DNA residue names with a "D"
- Rename atom name "O2" to "O"
- Rename atom names with a "*" character to use a "'" (single quote) instead

8.1.1.6.1 Initial 5' nucleotide residues

RNA residue names at the beginning of an RNA chain must be suffixed with a "5" character. Because this results in a three-character residue name, we will still be able to fit the residue name into the legal columns 18-20.

Further, 5' phosphate groups on initial RNA residues are not supported in the ffamber force field, so phosphate atoms (P, OP1, OP2, OP3), if present, must be removed from initial 5' RNA residues.

Figure 8.7: Modification of the initial RNA residue: (top) before editing, (bottom) after editing – note the removal of the atoms associated with the phosphate group

8.1.1.6.2 Final 3' nucleotide residues

Final 3' RNA and DNA residues are suffixed with a "3".

ATOM 899 P C N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 C N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 C N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' C N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' C N 45 0.977 -2.925 3.291 1 ATOM 904 C4' C N 45 1.719 -2.050 4.296 1 ATOM 905 O4' C N 45 2.129 -2.824 5.421 1 ATOM 906 C3' C N 45 2.995 -1.475 3.699 1 ATOM 907 O3' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.451 -4.470 6.510 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 -2.742 -3.375 3.776 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1	1.00 0.00 1.00 0.00	C P O O O C C O C O C O C N C O N C N C C
ATOM 900 OP1 C N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 C N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' C N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' C N 45 0.977 -2.925 3.291 1 ATOM 904 C4' C N 45 1.719 -2.050 4.296 1 ATOM 905 O4' C N 45 2.129 -2.824 5.421 1 ATOM 906 C3' C N 45 2.995 -1.475 3.699 1 ATOM 907 O3' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1	1.00 0.00 1.00 0.00	00000000000000000000000000000000000000
ATOM 901 OP2 C N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' C N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' C N 45 0.977 -2.925 3.291 1 ATOM 904 C4' C N 45 1.719 -2.050 4.296 1 ATOM 905 O4' C N 45 2.129 -2.824 5.421 1 ATOM 906 C3' C N 45 2.995 -1.475 3.699 1 ATOM 907 O3' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.658 -0.001 5.553 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -1.601 -4.193 1.640 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1	1.00 0.00 1.00 0.00	0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0
ATOM 902 O5' C N 45	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	0 C C O C O C O C N C O N C N C
ATOM 903 C5' C N 45 0.977 -2.925 3.291 1 ATOM 904 C4' C N 45 1.719 -2.050 4.296 1 ATOM 905 O4' C N 45 2.129 -2.824 5.421 1 ATOM 906 C3' C N 45 2.995 -1.475 3.699 1 ATOM 907 O3' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	C C O C O C N C O N C N C N C
ATOM 904 C4' C N 45 1.719 -2.050 4.296 1 ATOM 905 O4' C N 45 2.129 -2.824 5.421 1 ATOM 906 C3' C N 45 2.995 -1.475 3.699 1 ATOM 907 O3' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 -0.418 -2.617 3.203 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	С 0 0 0 0 0 0 0 0 0 0 0 0
ATOM 905 O4' C N 45 2.129 -2.824 5.421 1 ATOM 906 C3' C N 45 2.995 -1.475 3.699 1 ATOM 907 O3' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00	0 0 0 0 0 0 0 0 0 0 0
ATOM 906 C3' C N 45 2.995 -1.475 3.699 1 ATOM 907 O3' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00	С 0 0 0 0 0 0 0 0 0 0
ATOM 907 03' C N 45 2.755 -0.241 3.003 1 ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 02' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 02 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	0 0 0 0 0 N 0 N
ATOM 908 C2' C N 45 3.873 -1.280 4.933 1 ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	C O C N C O N C N C
ATOM 909 O2' C N 45 3.658 -0.001 5.553 1 ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	0 N C O N C
ATOM 910 C1' C N 45 3.430 -2.418 5.855 1 ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 900 OP1 RC3 N 45 -1.517 -3.805 3.064 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	C N C N C N
ATOM 911 N1 C N 45 4.384 -3.554 5.829 1 ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	и С О И С и
ATOM 912 C2 C N 45 5.595 -3.415 6.503 1 ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	C N C N C
ATOM 913 O2 C N 45 5.873 -2.380 7.076 1 ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	0 N C N C
ATOM 914 N3 C N 45 6.451 -4.470 6.510 1 ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00 1.00 0.00	N C N C
ATOM 915 C4 C N 45 6.143 -5.612 5.890 1 ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00 1.00 0.00	C N C
ATOM 916 N4 C N 45 7.007 -6.623 5.923 1 ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00 1.00 0.00	N C
ATOM 917 C5 C N 45 4.906 -5.761 5.197 1 ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00	C
ATOM 918 C6 C N 45 4.063 -4.711 5.190 1 TER 931 C N 45 ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1		
ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00	С
ATOM 887 C6 RC N 44 2.133 -9.174 2.039 1 ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1		
ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1		
ATOM 899 P RC3 N 45 -1.517 -3.805 3.064 1 ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1		
ATOM 900 OP1 RC3 N 45 -2.742 -3.375 3.776 1 ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00	C
ATOM 901 OP2 RC3 N 45 -1.601 -4.193 1.640 1 ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00	P
ATOM 902 O5' RC3 N 45 -0.418 -2.617 3.203 1 ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00	0
ATOM 903 C5' RC3 N 45 0.977 -2.925 3.291 1	1.00 0.00	0
	1.00 0.00	0
ATOM 904 C4' RC3 N 45 1.719 -2.050 4.296 1	1.00 0.00	C
	1.00 0.00	C
ATOM 905 04' RC3 N 45 2.129 -2.824 5.421 1	1.00 0.00	0
ATOM 906 C3' RC3 N 45 2.995 -1.475 3.699 1	1.00 0.00	C
ATOM 907 O3' RC3 N 45 2.755 -0.241 3.003 1	1.00 0.00	0
ATOM 908 C2' RC3 N 45 3.873 -1.280 4.933 1	1.00 0.00	C
	1.00 0.00	0
	1.00 0.00	C
	1.00 0.00	N
	1.00 0.00	C
	1.00 0.00	0
	1.00 0.00	N
	1.00 0.00	C
	1.00 0.00	N
		C
	1.00 0.00	C
TER 931 RC3 N 45		

Figure 8.8: Modification of final 3' RNA residue: (top) before editing, (bottom) after editing

ATOM	576	N	CPHE	76	5.995	-7.109	3.616	1.00	2.54	N
ATOM	577	CA	CPHE	76	6.033	-8.575	3.923	1.00	3.42	C
ATOM	578	С	CPHE	76	4.678	-9.203	3.574	1.00	4.09	C
ATOM	579	OC1	CPHE	76	3.672	-8.540	3.760	1.00	4.51	0

Figure 8.9: PDB file excerpt from villin.pdb. Green text shows where atom and residue names have been changed.

9 References

D.A. Case, T.E. Cheatham, III, T. Darden, H. Gohlke, R. Luo, K.M. Merz, Jr., A. Onufriev, C. Simmerling, B. Wang and R. Woods. The Amber biomolecular simulation programs. *J. Computat. Chem.* **26**, 1668-1688 (2005).

Friedrichs, M., Eastman, P., Vaidyanathan, V., Houston, M., Legrand, S., Beberg, A., et al. (2009). Accelerating Molecular Dynamic Simulation on Graphics Processing Units. *Journal of Computational Chemistry*, in press.

Glazer, D., Radmer, R.J., & Altman, R. (2008). Combining molecular dynamics and machine learning to improve protein function recognition. *Pac Symp Biocomput*, 332-343.

Herce, H., & Garcia, A. (2007). Molecular dynamics simulations suggest a mechanism for translocation of the HIV-1 TAT peptide across lipid membranes. *PNAS*, 104, 20805-20810.

Hess, B., Kutzner, C., van der Spoel, D., & Lindahl, E. (2008). GROMACS 4: Algorithms for Highly Efficient, Load-Balanced, and Scalable Molecular Simulation. *J. Chem. Theory Comput.*, 4, 435-447.

Humphrey, W., Dalke, A., & Schulten, K. (1996). VMD - Visual Molecular Dynamics. *J. Molec. Graphics*, 33-38.

Kasson, P., & Pande, V. (2008). Structural basis for influence of viral glycans on ligand binding by influenza hemagglutinin. *Biophysical Journal*, *95*, L48-L50.

Marszalek, P., & al., e. (1999). Mechanical unfolding intermediates in titin molecules. *Nature* , 402 (6757), 100-103.

Ponder, J.W. and Case, D.A. (2003). Force fields for protein simulations. *Adv. Prot. Chem.*, *66*, 27-85.

66 8BREFERENCES

Zagrovic, B. and Pande, V. (2003). Solvent viscosity dependence of the folding rate of a small protein: distributed computing study. *J. Comput. Chem.*, 24(12), 1432-1436.